

This update applies to the Communications Manual (Bulletin MN06040L Issue/Rev. 0.7 (11/95)) for all AccuLoad II's that are operating with AccuLoad - STD revision 26 and above firmware.

The version 26 firmware provides a program code (220) to take pulse samples every tenth of a second which are averaged to smooth out valve control on applications where the meter pulses are very cyclic.

Code	Description	Format	PV	PC	PC Ready Mode Only
220	Pulse Samples <i>Note: STD-26 and above firmware</i>	0-20	X		X